

Table of Contents

The Linux Thai HOWTQ	1
Poonlap Veeratanabutr, poon-v@fedu.uec.ac.jp.	1
1. Introduction	1
2. Thai Input and Output	1
2.1 Linux console	1
<u>Thai fonts</u>	1
Keyboard layout	
2.2 X Window system	
<u>Thai fonts</u>	
<u>Installing Thai fonts</u>	6
Thai keyboard layout There are two ways to map Thai keyboard on X window, using X	
Keyboard Extension (XKB) and using xmodmap. Please select how you map Thai	
keyboard. I recommend using XKB	
XKB and Thai keyboard layout.	
Thai keyboard layout with xmodmap	
3. Applications with Thai language	
3.1 Some X applications and Thai language	
txterm	
Emacs, Mule	
<u>vi</u>	
<u>pine</u>	
Netscape.	
Ss, Simple thai word Separator.	
Xzthai, X keyboard configurator + simple editor.	
3.2 Printing Thai document	
Latex and Thai language	
Latex's configuration for Thai language.	
Use Thai LaTeX filter	
Editing LaTex source file.	
3.3 X Application Resources.	
3.4 Thai Extension for Linux (TE).	
4. References and FTP sites	
4.1 Other documents of relevance. 4.2 Thai related stuffs.	
4.2 That related stuffs. 4.3 FTP and Web sites.	
5. Acknowledgments and Copyright.	
J. Acknowledgments and Copyright	1 /

Poonlap Veeratanabutr, poon-v@fedu.uec.ac.jp

v0.4, 4 August 1998

This document describes how to use Thai language with Linux. This will cover setting Thai fonts, Thai keyboard and some Thai applications.

1. Introduction

It's about one year that I didn't update this document. There were a lot of movement in Thai computing and using Linux in Thailand. For example, Linux boxes are used as server in many <u>schools in Thailand</u>.

The purpose of this document is to show how to set your Linux to use Thai language. I use Linux RedHat 5.0 as I wrote this document, so directories which I mention in this document may be different from other distribution.

First I would like to talk about Thai standard character set. Thai standard character set is TIS-620. There are also other Thai standard character sets such as ISO-IR-166, CP874, etc. Please see http://www.inet.co.th/cyberclub/trin/thairef/ for further information about Thai standard character set. TIS-620 is 8-bit character set. It has the same range as ISO-8859-1, so we can use applications that support ISO-8859-1 character set, but it does not mean those applications support Thai language.

Thai characters are different from English characters. There is a variation of position, normal position, character can be on other character, character can be under other character. There is no space between words. These are some problems in developing Thai supported application.

You can find the lastest version of Thai-HOWTO document from http://www.fedu.uec.ac.jp/ZzzThai/Linux. Your comment is welcome.

2. Thai Input and Output

2.1 Linux console

Thai characters do not display properly in Linux console. If you mainly use X window, you may pass this section.

Thai fonts

You can obtain Linux Thai console fonts which created by Mr. Phaisarn Techajaruwong from ZzzThai ftp site

For example, there is a font name "phaisarn.psf". Put it in /usr/lib/kbd/consolefonts/ directory. Then, you can load the new font from Linux console by command

%setfont phaisarn.psf

Keyboard layout

You can set keyboard behavior as you like by using loadkeys command. Usually, you use loadkeys to load the file located in /usr/lib/kbd/keytables. You can create a US/Thai keyboard-map file and save it in this directory. Here is a sample.

```
keycode 0 =
keycode 1 = Escape
                                 Escape
       alt keycode 1 = Meta_Escape
exclam
                                                    +0x0e5
                                                                      plus
         alt shift keycode 2 = Meta_exclam
keycode 3 = +two at
                                                                      0x0f1
                                                     +slash
        control keycode 3 = nul
         control shift keycode 3 = nul
         alt keycode 3 = Meta_two
        alt shift keycode 3 = Meta_at
keycode 4 = +three numbersign +underscore 0x0f2
        control keycode 4 = Escape
        alt keycode 4 = Meta_three
        alt shift keycode 4 = Meta_numbersign
keycode 5 = + \text{four} dollar + 0 \times 0 \times 0 0 \times 0 \times 13
         control keycode 5 = Control_backslash
         alt keycode 5 = Meta_four
        alt shift keycode 5 = Meta_dollar
keycode 6 = +five percent +0x0b6 0x0f4
         control keycode 6 = Control_bracketright
         alt keycode 6 = Meta_five
         alt shift keycode 6 = Meta_percent
                                 asciicircum +0x0d8 0x0d9
keycode 7 = +six
         control keycode 7 = Control_asciicircum
alt keycode 7 = Meta_six
         alt shift keycode 7 = Meta_asciicircum
alt keycode 8 = Meta_seven
keycode 9 = +eight asterisk control keycode 9 = Delete
                                                 +0x0a4 0x0f5
        alt keycode 9 = Meta_eight
keycode 10 = +nine parenleft +0x0b5 0x0d6
        alt keycode 10 = Meta_nine
keycode 11 = +zero parenright +0x0a8
                                                                      0x0f7
alt keycode 11 = Meta_zero
keycode 12 = +minus underscore +0x0a2
                                                                      0x0f8
         control keycode 12 = Control_underscore
         control shift keycode 12 = Control_underscore
         alt keycode 12 = Meta_minus
keycode 13 = +equal
                                                                      0x0f9
                                 plus
                                                     +0x0aa
        alt keycode 13 = Meta_equal
e 14 = Delete Delete
keycode 14 = Delete
                                                    Delete
                                                                      Delete
        alt keycode 14 = Meta_Delete

      keycode
      15 = Tab
      Tab
      Tab
      Tab

      alt
      keycode
      15 = Meta_Tab
      0x0f0

      keycode
      16 = +q
      Q
      +0x0e6
      0x0f0

      keycode
      17 = +w
      W
      +0x0e4
      quotedbl

      keycode
      18 = +e
      E
      +0x0d3
      0x0ae

      keycode
      19 = +r
      R
      +0x0be
      0x0b1

      keycode
      20 = +t
      T
      +0x0d0
      0x0b8

      keycode
      21 = +y
      Y
      +0x0d1
      0x0ed

      keycode
      22 = +u
      U
      +0x0d5
      0x0ea

      keycode
      23 = +i
      I
      +0x0c3
      0x0b3

keycode 15 = Tab
                                 Tab
                                                    Tab
                                                                      Tab
```

```
0x0b0
           control keycode 26 = Escape
           alt keycode 26 = Meta_bracketleft
           alt shift keycode 26 = Meta_braceleft
                                                                  +0x0c5
keycode 27 = +bracketright braceright
                                                                                      comma
          control keycode 27 = Control_bracketright
           alt keycode 27 = Meta bracketright
          alt shift keycode 27 = Meta_braceright
keycode 28 = Return Return Return Return
alt keycode 28 = 0x080d

keycode 29 = Control Control Control
keycode 30 = +a A +0x0bf 0x0c4

keycode 31 = +s S +0x0cb 0x0a6

keycode 32 = +d D +0x0a1 0x0af

keycode 33 = +f F +0x0b4 0x0e2

keycode 34 = +g G +0x0e0 0x0ac

keycode 35 = +h H +0x0e9 0x0e7

keycode 36 = +j J +0x0e8 0x0eb

keycode 37 = +k K +0x0d2 0x0c9

keycode 38 = +1 L +0x0ca 0x0c8

keycode 39 = +semicolon colon +0x0c7 0x0ab
          alt keycode 28 = 0 \times 080d
alt keycode 39 = Meta_semicolon
keycode 40 = +apostrophe quotedbl +0x0a7
                                                                                        period
          control keycode 40 = Control_g
          alt keycode 40 = Meta_apostrophe
keycode 41 = +grave asciitilde +minus
                                                                                      percent
          control keycode 41 = nul
alt keycode 41 = Meta_grave
keycode 42 = Shift Shift Shift
keycode 43 = +backslash bar +0x0a3
                                                                                      Shift
                                                                                      0x0a5
           control keycode 43 = Control_backslash
           alt keycode 43 = Meta_backslash
           alt shift keycode 43 = Meta_bar

        alt snift keycode 43 = Meta_bar

        keycode 44 = +z
        Z
        +0x0bc
        parenleft

        keycode 45 = +x
        X
        +0x0bb
        parenright

        keycode 46 = +c
        C
        +0x0e1
        0x0a9

        keycode 47 = +v
        V
        +0x0cd
        0x0ce

        keycode 48 = +b
        B
        +0x0d4
        0x0da

        keycode 49 = +n
        N
        +0x0d7
        0x0ec

        keycode 50 = +m
        M
        +0x0b7
        question

        keycode 51 = +comma
        less
        +0x0c1
        0x0b2

           alt keycode 51 = Meta_comma
           alt shift keycode 51 = Meta_less
keycode 52 = +period greater
                                                                                      0x0cc
                                                                  +0x0e3
         alt keycode 52 = Meta_period
          alt shift keycode 52 = Meta_greater
keycode 53 = +slash question +0x0bd
                                                                                        0x0c6
          control keycode 53 = Delete
           alt keycode 53 = Meta_slash
                                        Shift
keycode 54 = Shift
keycode 55 = KP_Multiply
                                                                Shift
                                                                                      Shift
keycode 56 = Alt Alt
keycode 57 = space space
                                                                Alt
                                                                                        Alt
                                         space
                                                                  space
                                                                                         space
          control keycode 57 = nul
           alt keycode 57 = Meta_space
control keycode 59 = F1
alt keycode 59 = Console_1
           control alt keycode 59 = Console_1
```

```
keycode 60 = F2
                                F12
                                                  Console_14
       control keycode 60 = F2
        alt keycode 60 = Console_2
control alt keycode 60 = Console_2 keycode 61 = F3 F13 Console_15 control keycode 61 = F3
        alt keycode 61 = Console_3
control alt keycode 61 = Console_3 keycode 62 = F4 F14 Console_16 control keycode 62 = F4
        alt keycode 62 = Console_4
control alt keycode 62 = Console_4
keycode 63 = F5 F15 Console_17
control keycode 63 = F5
alt keycode 63 = Console_5
control alt keycode 63 = Console_5
keycode 64 = F6 F16 Console_18
control keycode 64 = F6
alt keycode 64 = Console_6
control alt keycode 64 = Console_6
keycode 65 = F7 F17 Console_19
        control keycode 65 = F7
alt keycode 65 = Console_7
control alt keycode 65 = Console_7 keycode 66 = F8 F18 Console_20
        control keycode 66 = F8
        alt keycode 66 = Console_8
control alt keycode 66 = Console_8 keycode 67 = F9 F19 Console_21
        control keycode 67 = F9
        alt keycode 67 = Console_9
control alt keycode 67 = Console_9 keycode 68 = F10 F20 Console_22
        control keycode 68 = F10
        alt keycode 68 = Console_10
control alt keycode 68 = Console_10 keycode 69 = Num_Lock
keycode 69 = Num_Lock
keycode 70 = Scroll_Lock Show_Memory Show_Registers
       control keycode 70 = Show_State alt keycode 70 = Scroll_Lock
keycode 71 = KP_7
       alt keycode 71 = Ascii_7
keycode 72 = KP_8
       alt keycode 72 = Ascii_8
keycode 73 = KP_9
       alt keycode 73 = Ascii_9
keycode 74 = KP\_Subtract
keycode 75 = KP_4
      alt keycode 75 = Ascii_4
keycode 76 = KP_5
       alt keycode 76 = Ascii_5
keycode 77 = KP_6
       alt keycode 77 = Ascii_6
keycode 78 = KP_Add
keycode 79 = KP_1
      alt keycode 79 = Ascii_1
keycode 80 = KP_2
       alt keycode 80 = Ascii_2
keycode 81 = KP_3
       alt keycode 81 = Ascii_3
keycode 82 = KP_0
        alt keycode 82 = Ascii_0
```

```
keycode 83 = KP_Period
      altgr control keycode 83 = Boot
                    keycode 83 = Boot
       control alt
keycode 84 = Last_Console
keycode 85 =
keycode 86 = less
                             greater
       alt keycode 86 = Meta_less
keycode 87 = F11 F11
                                               Console_23
       control keycode 87 = F11
              keycode 87 = Console_11
       control alt keycode 87 = Console_11
88 = F12 F12 C
keycode 88 = F12
                                               Console_24
       control keycode 88 = F12
            keycode 88 = Console_12
       alt
       control alt keycode 88 = Console_12
keycode 89 =
keycode 89 = keycode 90 = keycode 91 = keycode 92 = keycode 93 =
keycode 94 =
keycode 95 =
keycode 96 = KP\_Enter
keycode 97 = Control
keycode 98 = KP_Divide
keycode 99 = Control_backslash
       control keycode 99 = Control_backslash
       alt keycode 99 = Control_backslash
keycode 100 = AltGr_Lock
keycode 101 = Break
keycode 102 = Find
keycode 103 = Up
keycode 104 = Prior
       shift keycode 104 = Scroll_Backward
keycode 105 = Left
       alt keycode 105 = Decr_Console
keycode 106 = Right
       alt keycode 106 = Incr_Console
keycode 107 = Select
keycode 108 = Down
keycode 109 = Next
       shift keycode 109 = Scroll_Forward
keycode 110 = Insert
keycode 111 = Remove
       altgr control keycode 111 = Boot
       control alt keycode 111 = Boot
keycode 112 =
keycode 113 =
keycode 114 =
keycode 115 =
keycode 116 =
keycode 117 =
keycode 118 =
keycode 119 =
keycode 120 =
keycode 121 =
keycode 122 =
keycode 123 =
keycode 124 =
keycode 125 =
keycode 126 =
keycode 127 =
```

```
string F1 = "\033[[A"]
string F2 = "\033[[B"]]
string F3 = "\033[[C"]
string F4 = "\033[[D"]
string F5 = " \setminus 033 [[E"]]
string F6 = "\033[17~"]
string F7 = "\033[18~"]
string F8 = "\033[19~"]
string F9 = "\033[20~"
string F10 = "\033[21~"]
string F11 = "\033[23~"]
string F12 = "\033[24~"]
string F13 = "\033[25~"]
string F14 = "\033[26~"]
string F15 = "\033[28~"]
string F16 = "\033[29~"]
string F17 = "\033[31~"]
string F18 = "\033[32~"]
string F19 = "\033[33~"]
string F20 = "\033[34~"]
string Find = "\033[1~"]
string Insert = "\033[2~"]
string Remove = "\033[3~"
string Select = "\033[4~"]
string Prior = "\033[5~"]
string Next = "\033[6~"
string F21 = ""
string F22 = ""
string F23 = ""
string F24 = ""
string F25 = ""
string F26 = ""
```

Suppose you save this file as thai.map. From Linux console, use command loadkeys to load thai.map.

```
%loadkeys thai.map
```

You can switch to Thai keyboard by pressing the right Alt key. If you want to switch the keyboard back, press the right Alt key again.

2.2 X Window system

Thai fonts

You can obtain Thai fonts in bdf format or pcf format from internet. You can also use scalable fonts such as Type1 or TrueType fonts. But I will not describe about these.

Installing Thai fonts

You must log in as root. Let's put Thai fonts in /usr/X11R6/lib/X11/fonts/misc/, this is a default font path. Change directory to /usr/X11R6/lib/X11/fonts/misc/ and run command

```
%mkfontdir
%xset fp rehash
```

If you put Thai fonts in different directory, you must use xset to add the new font path. Please see man-page for further information. You can check the new fonts by running command xlsfonts and see whether there are Thai fonts or not. If you can not see any Thai fonts from this command, you may need to restart X window.

Thai keyboard layout There are two ways to map Thai keyboard on X window, using X Keyboard Extension (XKB) and using xmodmap. Please select how you map Thai keyboard. I recommend using XKB.

XKB and Thai keyboard layout.

Beginning with XFree86 3.1.2D, you can use the new X11R6.1 XKEYBOARD extension to manage the keyboard layout. This is very helpful.

During X server configuration with xf86config you will be asked about XKB, if you want to to set Thai keyboard layout for your system, say yes. There are a list of pre-configured keymaps. Choose Standard 101-key, Thai encoding.

XF86Setup is the graphical X server configuration utility for XFree86 X server. It is easier than traditional xf86config. You can select a keyboard layout easily with this tool.

Ther are many choices of keyboard switch key to select. The default is LeftAlt+RightShift switch to Thai and LeftAlt+LeftShift switch to US. You can type Thai characters in any applications which support ISO-8859-1 character set, but don't forget to use Thai fonts with those applications too.

I found that pre-configured keymaps that came with XFree86-3.2 is not correct. You may not be able to type THO THUNG which located at " 5 key " . To fix this problem, you should add the line

```
key <AE05> { [], [ paragraph, ocircumflex ] };
```

in the file /usr/X11R6/lib/X11/xkb/symbols/th as the example.

You can not type SORUSI also. Please change the line from

```
key <AC08> { [], [ Ograve, eacute ] };

to

key <AC08> { [], [ Ograve, Eacute ] };
```

Note that eacute is equal to MAITHO and Eacute is equal to SORUSI.

There are also XKB extension utilities such as setxkbmap, xkbcomp, etc. Please see man-page for more

information. I recommend to use xkbvled. The leds will be on when you are using Thai keyboard so you can know your keyboard's status.

The following is part of XF86Config file about keyboard section. If you want to configure the keyboard by hand, change the content of /usr/X11R6/lib/X11/XF86Config as an example below. This configuration uses the default toggle key.

```
Section "Keyboard"
Protocol "Standard"
AutoRepeat 500 5
LeftAlt Meta
RightAlt Meta
ScrollLock Compose
RightCtl Control

# XkbDisable
XkbKeycodes "xfree86"
XkbTypes "default"
XkbCompat "default"
XkbSymbols "us(pc101)"
XkbRules "xfree86"
XkbModel "pc101"
XkbLayout "th"
```

If you use XKB extension, Thai keyboard mapping with xmodmap may not work. See XF86Config man-page for mor information.

Thai keyboard layout with xmodmap

You can use the utility xmodmap to map Thai keyboard. Normally xmodmap is used to load a keyboard configured file. For most Linux distributions, when you start X window with startx, X server will find .Xmodmap in /usr/X11R6/lib/X11/xinit/ first. If .Xmodmap does not exist, X server will find .Xmodmap in your home directory. Please see the content of /usr/X11R6/lib/X11/xinit/xinitrc.

The following is the sample of .Xmodmap for Thai Kedmanee keyboard layout.

```
! Linux/XFree86 Thai Kedmanee layout (based on US keyboard)
! Use ScrollLock to switch to Thai keyboard.
! This file will work with XFree86 only.
keycode 0x09 = Escape
keycode 0x43 = F1
keycode 0x44 = F2
keycode 0x45 = F3
kevcode 0x46 = F4
keycode 0x47 = F5
keycode 0x48 = F6
keycode 0x49 = F7
keycode 0x4A = F8
keycode 0x4B = F9
keycode 0x4C = F10
keycode 0x5F = F11
keycode 0x60 = F12
```

1	0		Duint			
keycode keycode			Print Mode_switch	XF86ModeLock		
keycode			Pause	AFOUNDUELOCK		
keycode			grave	asciitilde	minus	percent
keycode			1	exclam	0x0e5	plus
keycode			2	at	slash	0x0f1
keycode			3	numbersign	underscore	0x0f2
keycode			4	dollar	0x0c0	0x0f3
keycode			5	percent	0x0b6	0x0f4
keycode			6	asciicircum	0x0d8	0x0d9
keycode			7	ampersand	0x0d6	0x0df
keycode			8	asterisk	0x0a4	0x0f5
keycode			9	parenleft	0x0b5	0x0f6
keycode			0	parenright	0x0a8	0x0f7
keycode			minus	underscore	0x0a2	0x0f8
keycode			equal	plus	0x0aa	0x0f9
keycode			backslash	bar	0x0a3	0x0a5
keycode			BackSpace			
keycode			Insert			
keycode			Home			
keycode			Prior			
keycode			Num_Lock			
keycode	0x70	=	KP_Divide			
keycode			KP_Multiply			
keycode			KP_Subtract			
keycode			Tab			
keycode	0x18	=	q	Q	0x0e6	0x0f0
keycode	0x19	=	W	W	0x0e4	quotedbl
keycode	0x1A	=	е	E	0x0d3	0x0ae
keycode	0x1B	=	r	R	0x0be	0x0b1
keycode	0x1C	=	t	T	0x0d0	0x0b8
keycode	0x1D	=	У	Y	0x0d1	0x0ed
keycode	0x1E	=	u	U	0x0d5	0x0ea
keycode	0x1F	=	i	I	0x0c3	0x0b3
keycode	0x20	=	0	0	0x0b9	0x0cf
keycode	0x21	=	p	P	0x0c2	0x0ad
keycode			bracketleft	braceleft	0x0ba	0x0b0
keycode			bracketright	braceright	0x0c5	comma
keycode			Return			
keycode			Delete			
keycode			End			
keycode			Next			
keycode			KP_7			
keycode			KP_8			
keycode			KP_9			
keycode			KP_Add			
keycode			Caps_Lock	7	001- 5	00 - 4
keycode			a	A	0x0bf	0x0c4
keycode			S	S	0x0cb	0c0a6
keycode			d	D	0x0a1	0x0af
keycode			f	F	0x0b4	0x0e2
keycode			g h	G	0x0e0	0x0ac
keycode			h	H J	0x0e9 0x0e8	0x0e7
keycode			j k	K	0x0e8 0x0d2	0x0eb
keycode			k 1	L L	0x0d2 0x0ca	0x0c9 0x0c8
keycode keycode			semicolon	colon	0x0ca 0x0c7	0x0c8 0x0ab
keycode			apostrophe	quotedbl	0x0c7 0x0a7	period
keycode			KP_4	quoccanı	onou i	PCTTOU
keycode			KP_5			
keycode			KP_6			
keycode			Shift_L			
						

```
0x0bc
keycode 0x34 = z
                                                             parenleft
                                              0x0bb
keycode 0x35 = x
                                                             parenright
                               Χ
keycode 0x36 = c
                               С
                                              0x0e1
                                                             0x0a9
                              V
keycode 0x37 = v
                                              0x0cd
                                                             0x0ce
keycode 0x38 = b
                             В
                                             0x0d4
                                                             0x0da
                                             0x0d7
keycode 0x39 = n
                             N
                                                             0x0ec
keycode 0x3A = m
                             M
                                             0x0b7
                                                             question
keycode 0x3B = comma less
keycode 0x3C = period greater
keycode 0x3D = slash question
keycode 0x3E = Shift P
                                             0x0c1
                                                             0x0b2
                             greater 0x0e3 question 0x0bd
                                                             0x0cc
                                                             0x0c6
keycode 0x62 = Up
keycode 0x57 = KP_1
keycode 0x58 = KP_2
keycode 0x59 = KP_3
keycode 0x6C = KP\_Enter
keycode 0x25 = Control_L
keycode 0x40 = Alt_L
                             Meta_L
keycode 0x41 = space
keycode 0x71 = Alt_R
                             Meta_R
keycode 0x6D = Control_R
keycode 0x64 = Left
keycode 0x68 = Down
keycode 0x66 = Right
keycode 0x5A = KP_0
keycode 0x5B = KP\_Decimal
clear Shift
clear Lock
clear Control
clear Mod1
clear Mod2
clear Mod3
clear Mod4
clear Mod5
add
      Shift = Shift_L Shift_R
      Lock = Caps_Lock
add
add
      Control = Control_L Control_R
add
      Mod1 = Alt_L Alt_R
add Mod2 = Mode_switch
```

Just put . X modmap in your home directory will be OK. When you start X window, X server will load this file.

You can also load . Xmodmap from command line.

```
%xmodmap ~/.Xmodmap
```

In above . Xmodmap file, US/Thai switch key is assigned to keycode 0x4E (78), Scroll Lock key, with the statement

```
keycode 0x4E = Mode_switch XF86ModeLock
```

XF86ModeLock is the special keysym for XFree86 X server. If you don't add this keysym, you have to hold the scroll lock key while you are typing Thai characters. Note that if you use commercial X server, some keycodes are different. You may have to map keyboard by yourself. See man-pages of X and xev for further

information.

Note: If you are using XFree86 version 3.1.2D or later, you need to add the line XkbDisable in keyboard section of XF86Config file. You may config the keyboard section like the following sample.

```
Section "Keyboard"

Protocol "Standard"
AutoRepeat 500 5
LeftAlt Meta
RightAlt ModeShift
ScrollLock ModeLock
RightCtl Compose
XkbDisable
EndSection
```

3. Applications with Thai language

This is the tricky part. Most applications support ISO-8859-1 character set. For example, emacs can display ISO-8859-1 character. If we set emacs to display ISO-8859-1 and use Thai font, you can edit Thai document with emacs. But this is not a good policy. You should avoid using this trick as possible. What we need is Thai locale or Thai supported applications to manage these things.

To make X window application displays Thai font, you should run the application with -fn option. For example,

```
%xedit -fn thai8x16
```

Note that thai8x16 is just a one of Thai font names. You can see all available fonts by command xlfonts. If you don't want to fill -fn option every time you run application. You should set Thai font in your ~/.Xdefaults or ~/.Xresources like this

XTerm*font: thai8x16

3.1 Some X applications and Thai language

txterm

txterm is Thai version of xterm. There are several programs running under xterm such as shell, pine, vi, less, etc. We can type Thai characters without any problems with txterm. Txterm also provides its own Thai input method by pressing "F1" key. Txterm will use fonts thai 9x13 as default Thai font. You can change this by add -fn option.

You can get txterm from Thaigate or ZzzThai.

bash shell:

Normally, shell accepts only ASCII character set. To type Thai characters in shell command line, you should set environment LC_CTYPE to iso_8859_1.

I don't set LC_CTYPE environment variable to iso_8859_1 because this environment variable will effect other applications too. With bash shell, you can specify which environment variable to be passed to the application. For example, I can make a fake Thai X terminal with this syntax.

```
LC_CTYPE=iso_8859_1 xterm -fn thai8x16
```

This xterm display Thai characters well, but not good for typing Thai characters. I strongly recommend you to use txterm.

ls:

If you name a filename in Thai. Issue the command as

```
ls -N
```

You may set alias in ~/.bashrc or ~/.cshrc, so you can type ls without option. If you don't use ls with -N option, you may see Thai filename as ?????.

Emacs, Mule

Mule stands for "Multilingual Enhancement to GNU Emacs". It has the same functions as emacs and supports many languages. Mule provides its own input method, so you don't need any configuration for typing Thai. You needs only Thai fonts for mule which you can get from, ZzzThai or Etl site. These Thai fonts are fixed width fonts

You need some configuration for mule. Puts the following lines in your .emacs.

```
;; Thai System, add in .emacs
;;
(set-file-coding-system-for-read '*tis620*)
(set-default-file-coding-system '*tis620*)
(set-display-coding-system '*tis620*)
(set-keyboard-coding-system '*tis620*)
(setq-deafault quail-current-package (assoc "thai" quail-package-alist))
```

Add the following lines in .Xdefaults.

When you hold shift key and press left mouse's button, you can select Thai fonts to display in mule window. To type Thai characters, press "Ctrl + 1". To type English, press "Ctrl + 1" again.

You can get mule from <u>ElectroTechnical Laboratory(ETL)</u>

vi

Vi should be run on txterm.

pine

In the past, we could not send 8-bit characters through E-mail. Now, although mail transfer agent can handle 8-bit characters but some old mail transfer agent can not. We can send Thai e-mail by using e-mail application that supports MIME (Multipurpose Internet Mail Extensions) E-mail applications that support MIME are pine, elm, Netscape mail, etc.

Put the following definition in your ~/.pinerc file:

```
character-set=ISO-8859-1
```

This can also be set via the Setup option in pine window. You can find it under Config. You can read Thai news from pine, too.

Pine should be run in txterm.

Netscape

If you have Thai fonts in your system. Just set Thai font from preference. Thai fonts will appear in User defined area. See http://www.fedu.uec.ac.ip/ZzzThai/unix for setting Thai language on Netscape.

Some movement about Thai Mozilla project at http://members.xoom.com/inThai/mozthai.html.

Ss, Simple thai word Separator

ss is a dictionary based Thai word separation program similar to cttex. It can be used to insert a configurable string between Thai words. It can also show words that cannot be found in the dictionary. More words can be added to the dictionary. Developed by Mr.Teera Kittichareonpot.

We can use this program to insert < WBR > tag between Thai words in html file. Browser will display Thai homepage better than normal html document.

Xzthai, X keyboard configurator + simple editor

Xzthai, this is the Tcl/Tk application for mapping Thai keyboard on any keyboard with graphical user interface. Also provides simple editor and keyboard layout figure. It actually uses xmodmap program in background to map Thai keyboard. This may be useful for commercial X server and X server on UNIX.

3.2 Printing Thai document

Thai2ps is used to convert plain text file to postscript file. You can use ghostscript(gs) to print your Thai document. For better quality document, you have to use (La)TeX.

Latex and Thai language

Dr. Manop Wongsaisuwan first tried to use Thai language with latex. He wrote some perl script as filter for latex source code that contains Thai language. Then pass the result to latex. Mr. Vuthichai Ampornaramvech used this concept and wrote a program in C language, cttex, to handle this. It runs faster and makes Thai word segmentation based on dictionary. Cttex also fixes the position of Thai characters in

word, so SARA and WANNAYUK will be placed in the beautiful position.

You can find Thai latex filter from http://thaigate.nacsis.ac.jp/files/ttex.html.

Latex's configuration for Thai language

You must have latex installed in your computer. First, download Thai postscript (Type1) fonts, tfm fonts and Thai style file. These fonts are needed by Latex. This is the list of files you should download.

```
tfm fonts:
    dbtt.tfm    dbttb.tfm    dbttbi.tfm    dbtti.tfm
postscript fonts:
    dbtt.pfa    dbttb.pfa    dbttbi.pfa    dbtti.pfa
style files:
    thai.sty sakka.sty
Thai Latex filter:
    cttex
Sample Latex file:
    ttex.ttex test.ttex
```

There is latex's directory at /usr/lib/texmf/texmf/ (RedHat 5.0). I will call /usr/lib/texmf/texmf/ as " \$texroot ". We will concentrate at \$texroot/texmf/ directory. In \$texroot/texmf/ directory, there are many files about tex's configuration. You have to edit files in dvips, fonts, tex subdirectories.

Add the following lines to \$texroot/texmf/dvips/misc/psfonts.map

```
dbtt DBThaiText <dbtt.pfa
dbttb DBThaiTextBold <dbttb.pfa
dbttbi DBThaiTextBoldItalic <dbttbi.pfa
dbtti DBThaiTextItalic <dbtti.pfa</pre>
```

Make a new directories and copy files to the appropriate directories.

```
%mkdir /usr/lib/texmf/texmf/fonts/tfm/public/thai
%mkdir /usr/lib/texmf/texmf/fonts/type1/public/thai
%mkdir /usr/lib/texmf/texmf/tex/generic/thai
%cp *.tfm /usr/lib/texmf/texmf/fonts/tfm/public/thai
%cp *.pfa /usr/lib/texmf/texmf/fonts/type1/public/thai
%cp *.sty /usr/lib/texmf/texmf/tex/generic/thai
```

Run texhash or MakeTeXls-R(in some system) to update Tex database.

```
%/usr/bin/texhash
texhash: updating /usr/lib/texmf/texmf/ls-R ...
texhash: Done.
```

Use Thai LaTeX filter

We can use cttex as filter like this,

```
%cttex < ttex.ttex > ttex.tex
C-TTeX $Revivsion: 1.15 $
Usage : cttex [cutcode] < infile > outfile
Usage : cutcode=0 forces operation in HTML mode.
```

```
Build-in dictionary size: 9945 words 343
Done
%latex ttex.tex
...
%xdvi ttex.dvi
```

You can convert dvi file to postscript file by,

```
%dvips -o ttex.ps ttex.dvi
```

Finally, you can print ttex.ps by using gs or lpr. You must configure printer before printing. See man-pages of printcap, gs, lpr for more information.

Editing LaTex source file

For new latex user, lyx is helpful. But I recommend to use mule to edit Thai latex source file because mule supports Thai language and it is a powerful editor. You may take a look a <u>Thai Latex tutorial</u>.

3.3 X Application Resources

Because Xt based applications allow user to configure the applications by resources. We can make the menu or label to be Thai language.

For example, if you want xman to display Thai labels. You may add these lines in your .Xdefaults

```
!! Xman section
Xman*Font: thai8x16
Xman*helpButton.Label: aèÇÂ
Xman*quitButton.Label: fí;
Xman*manpageButton.Label: ¤ÙèÁ×Í;ÒÃãaé
```

You can use the same idea to set window manager to be more Thai environment too.

3.4 Thai Extension for Linux (TE)

Thai Extension for Linux is a installation package comes with applications and Thai fonts. You don't have to configure Linux system and applications by yourself. Let TE do configuration task for you. After installation, you can use Thai language suddenly. Get TE from ftp://fedu.uec.ac.jp/pub/thai/UEC/ZzzThai/Software/Linux/

4. References and FTP sites

4.1 Other documents of relevance

The HOWTOs ought to be available from all mirrors of sunsite.unc.edu.

The Linux Danish/International HOWTO by Niels Kristian Bech Jensen

The Linux Cyrillic HOWTO by Alexander L. Belikoff

The Keystroke mini-HOWTO by Zenon Fortuna.

The Locales mini-HOWTO by Peeter Joot. (This one is mainly for developers.)

The ISO-8859-1 FAQ and Programming for Internationalization FAQ (plus much more) by Michael Gschwind is available from <u>his homepage</u>.

4.2 Thai related stuffs

- " NACSIS R& D Thai Project Page ", http://thaigate.nacsis.ac.jp
 - Information about Thai computing.
 - Discussion groups in Thai language, such as thai-1 (Thai Mailing list), Thai news, etc.
 - Thai references and Thai softwares.
 - Thai Latex filter.
- " ZzzThai Project ", http://www.fedu.uec.ac.jp
 - Most softwares and Thai fonts introduced here can download from ZzzThai.
 - Describe how to use Thai with 3 main computer platforms, UNIX like, Windows and Mac.
 - Linux information at http://www.fedu.uec.ac.jp/ZzzThai/Linux, TE, Thai LaTeX tutorial, etc.
 - By The group of students at The University of Electro-Communications, Tokyo.
- " Vuthichai's Page ", http://www.ctrl.titech.ac.ip:80/~vuthi/
 - Information about Thai computing by Mr. Vuthichai Ampornaramveth.
- " An annotated reference to the Thai implementations ", http://www.inet.co.th/cyberclub/trin/thairef/
 - Information about Thai character standard.
 - By Mr.Trin Tantsetthi.
- " X window and Thai language ", http://members.xoom.com.cwg.x11th/
 - By Mr.Rawat S.Pirom
- " SchoolNet Internet Sever ", http://www.school.net.th/linux-sis/
 - Using Linux in School, Thailand.
 - By <u>NECTEC</u> (National Electronics and Computer Technology Center).
- "Thai Open Source Development", http://members.xoom.com/inThai
 - Mozilla Thai enabling.
 - Open source Thai softwares and Libraries.
 - By Mr.Samphan Raruenrom
- "Linux Thai Project", http://www.geocities.com/SiliconValley/8302
 - Information about Linux in Thai language.

• By Kaiwal Development Team.

"ThaiLinux unofficial Webboard", http://lulu.mptc.eng.cmu.ac.th/HyperNews/get/ThaiLinux.html

- Questions and answers about Linux in Thai language.
- By Mr.Pruet Boonma

"Thai Linux installation project", http://www.geocities.com/Tokyo/Bay/4521/

• Installation guide in Thai language

4.3 FTP and Web sites

Most softwares and Thai fonts which introdued in this howto.

- ftp://ftp.fedu.uec.ac.jp/pub/thai/UEC/ZzzThai/Software/Linux
- http://thaigate.nacsis.ac.jp/files/index.html
- http://www.nectec.or.th/pub/software/i18n/thai

Mule

• ftp://etlport.etl.go.jp/pub/mule

Ss

• http://members.xoom.com/theera/ss/

<u>SunSite</u> and mirrors. doc/howto has the above mentioned HOWTOs. utils/nls and subdirectories contain files related to National Language Support. Developers should take a look at locale-tutorial-0.8.txt.gz, locale-pack-0.8.tar.gz and cat-pack.tar.gz.

<u>The GNU archives</u> has the recode package for character table conversion, the ABOUT-NLS file and the gettext package for locale support of some GNU applications and (of course) the latest versions of GNU emacs.

5. Acknowledgments and Copyright

Some parts of this HOWTO comes from The Linux Danish/International HOWTO by Thomas Petersen, petersen@post1.tele.dk (the original author) and Niels Kristian Bech Jensen, nkbj@image.dk.

Thank you to Phaisarn Techajaruwong for building Thai fonts and valuable discussion.

Thank you to Thai students at The University of Electro-Communications and Mr. Vuthichai Ampornaramveth for every help.

This HOWTO is copyrighted by Poonlap Veeratanabutr, poon-v@fedu.uec.ac.jp. It is distributed as other Linux HOWTOs under the terms described below.

Linux HOWTO documents may be reproduced and distributed in whole or in part, in any medium physical or electronic, as long as this copyright notice is retained on all copies. Commercial redistribution is allowed and

encouraged; however, the authors would like to be notified of any such distributions.

All translations, derivative works, or aggregate works incorporating any Linux HOWTO documents must be covered under this copyright notice. That is, you may not produce a derivative work from a HOWTO and impose additional restrictions on its distribution. Exceptions to these rules may be granted under certain conditions; please contact the Linux HOWTO coordinator at the address given below.

If you have questions, please contact Tim Bynum, the Linux HOWTO coordinator, at linux-howto@sunsite.unc.edu via email.